P Tower Serial Communication Protocol

Contents

Introduction	P.2
P.1 Conceptual View	P.2
P.2 PC and Tower Communication	P.3
P.3 Packet Structure	P.4
P.4 Packets Transmitted from Tower to PC	P.5
P.5 Packets Transmitted from PC to Tower	P.7
P.6 Packet Acknowledgement	P.9
P.7 PC Communication Parameters.	P.11
P.7.1 Baud Rate and Virtual Com Ports	
P.7.2 Baud Rate and Data Format	

Introduction

This document outlines the communication protocol between the PC and the Tower microcontroller board.

P.1 Conceptual View

The PC or Tower can initiate a transfer of serial information at any time (asynchronously) using the Universal Serial Bus (USB). Information is transferred in packets, with each packet consisting of 5 bytes. A conceptual view of communication between the PC and the Tower is shown below:

Conceptual view of information transfer between PC and Tower





Figure 5.1

Sometimes a transmitted packet will request a response from the receiver. In this case, a response to the command is initiated once the command has been carried out (or attempted to be carried out).

P.2 PC and Tower Communication

A typical picture of the PC and Tower communicating is shown below:



PC and Tower communicating

Figure 5.2

The Tower is continually updating the PC with information regarding the state of the various inputs and outputs of the module, such as push buttons, LEDs, A/D results and PWM duty cycles. This state information is only sent on start up and when the state of the Tower module changes – this prevents the PC from receiving many packets with the same information, which wastes processing time.

The PC will occasionally send a request packet to the Tower, asking it to carry out some task. It may or may not specify for the Tower to acknowledge that the request has been carried out successfully. If the PC does specify an acknowledgement, then the Tower will respond with a response packet.

P.3 Packet Structure

Each packet of information contains 5 bytes as follows:

Packet structure




Figure 5.3

The command byte contains a command number, as listed in the tables that follow. The use of the three parameter bytes depends on the particular command being sent. The checksum is the exclusive-or (XOR) of the four preceding bytes and is used as a simple means to detect most transmission errors (corruption of a packet) and for packet synchronization.

P.4 Packets Transmitted from Tower to PC

The following table lists the packets that can be sent by the Tower to the PC:


Command	Data Stream
0x04	Tower Startup
	Parameter 1: 0
	Parameter 2: 0
	Parameter 3: 0
	Note: The Tower will issue this command upon startup to allow
	the PC to update the interface application and the Tower.
0.00	Typically, setup data will also be sent from the Tower to the PC.
0x08	Flash – Read byte
	Parameter 1: address offset (0-7)
	Parameter 2: 0
0.00	Parameter 3: data
0x09	Special – Master alarm
	Parameter 1: 12
	Parameter 2: 0
	Parameter 3: 2
000	Note: If the PC receives this then the Tower is overloaded.
0x09	Special – Tower version Parameter 1: 'v' = version
	Parameter 2: Major Version Number
	Parameter 3: Minor Version Number (out of 100)
	Note: e.g. V1.3 has a major version number of 1 and a minor
	version number of 30.
0x0A	Protocol – Mode
OXO11	Parameter 1: 1
	Parameter 2: 0 = asynchronous
	1 = synchronous
	Parameter 3: 0
0x0B	Tower Number
	Parameter 1: 1
	Parameter 2: LSB
	Parameter 3: MSB
	Note: The Tower number is an unsigned 16-bit number.

0x0C	Time
	Parameter 1: hours (0-23)
	Parameter 2: minutes (0-59)
	Parameter 3: seconds (0-59)
0x0D	Tower Mode
	Parameter 1: 1
	Parameter 2: LSB
	Parameter 3: MSB
	<u>Note:</u> The Tower mode is just an unsigned 16-bit number – it is
	usually declared as an enumerated type.
0x10	Accelerometer - Value
	Parameter 1: x-axis MSB
	Parameter 2: y-axis MSB
	Parameter 3: z-axis MSB
0x50	Analog Input – Value
	Parameter 1: analog channel (0-7)
	Parameter 2: LSB
	Parameter 3: MSB
0x51	Analog Output – Value
	Parameter 1: analog channel (0-1)
	Parameter 2: LSB
	Parameter 3: MSB

EXAMPLE P.1 Example Packet Sent from the Tower

For example, if the Tower were informing the PC that its version number is 1.3, then the packet would be:

Example packet sent from Tower



P.5 Packets Transmitted from PC to Tower

The following table lists the packets that can be sent by the PC:


Command	Data Stream	
0x04	Special - Get startup values	
	Parameter 1: 0	
	Parameter 2: 0	
	Parameter 3: 0	
	Note: The PC will issue this command upon startup to retrieve	
	the state of the Tower to update the interface application.	
0x07	Flash – Program byte	
	Parameter 1: address offset (0-8)	
	Parameter 2: 0	
	Parameter 3: data	
	Note: The address offset has a range of 0x00 to 0x08.	
0.00	An address offset of 0x08 will ERASE the entire Flash sector.	
0x08	Flash – Read byte	
	Parameter 1: address offset (0-7)	
	Parameter 2: 0 Parameter 3: 0	
0x09	Note: The address offset has a range of 0x00 to 0x07.	
0x09	Special – Get values Parameter 1: 'g'	
	Parameter 2: 'i'	
	Parameter 3: CR	
	Note: The Tower will send switch, counter and analog values,	
	which the PC may or may not use.	
0x09	Special - Start bootloader	
	Parameter 1: 'b'	
	Parameter 2: '1'	
	Parameter 3: CR	
0x09	Special – Toggle debug mode	
	Parameter 1: 'd'	
	Parameter 2: 'j'	
	Parameter 3: CR	
0x09	Special – Get version	
	Parameter 1: 'v'	
	Parameter 2: 'x'	
	Parameter 3: CR	
0x0A	Protocol – Mode	
	Parameter 1: 1 = get Protocol mode	
	2 = set Protocol mode	
	Parameter 2: 0 = asynchronous for a "set", 0 for a "get"	
	1 = synchronous for a "set", 0 for a "get"	
	Parameter 3: 0	

0x0B	Tower Number
	Parameter 1: 1 = get Tower number
	2 = set Tower number
	Parameter 2: LSB for a "set", 0 for a "get"
	Parameter 3: MSB for a "set", 0 for a "get"
	Note: The Tower number is an unsigned 16-bit number.
0x0C	Set Time
	Parameter 1: hours (0-23)
	Parameter 2: minutes (0-59)
	Parameter 3: seconds (0-59)
0x0D	Tower Mode
	Parameter 1: 1 = get Tower mode
	2 = set Tower mode
	Parameter 2: LSB for a "set", 0 for a "get"
	Parameter 3: MSB for a "set", 0 for a "get"
	<u>Note:</u> The Tower mode is just an unsigned 16-bit number – it is
	usually declared as an enumerated type.

EXAMPLE P.2 Example Packet Sent from the PC

For example, if the PC were requesting the Tower to write 0xA5 to Flash memory with an address offset of 5, then the packet would be:

Example packet sent from PC



P.6 Packet Acknowledgement

The command ID has bit 7 (the most significant bit) reserved for packet acknowledgement purposes. The transmitter sets bit 7 to a 1 to request an acknowledgement, and leaves it cleared to 0 for no required acknowledgement.

The receiver, upon receiving a packet with an acknowledgement request, will firstly attempt to carry out the requested command. It will then either set bit 7 to indicate that the command was carried out successfully (an ACK), or clear it to 0 to indicate that the command could not be carried out (a NAK), and send the packet back to the requester.

For example, if the PC sends the following packet to write 0xA5 to Flash memory with address offset 5:




Figure 5.4

then the Tower will respond with the same packet, indicating it was carried out successfully.

However, if the PC asked to write to address offset 10 (which is out of range), then the Tower would respond with:





Figure 5.5


Note that the most significant bit of the command has been cleared, indicating that the requested command could not be carried out.

EXAMPLE P.3 Example of Packet Acknowledgement


The Tower PC Interface sends a normal "Startup" packet:




The Tower responds with:



The Tower PC Interface now sends a "Startup" packet with an acknowledgement request (the MSB is set in the command):



The Tower responds with:



Note that the Tower board has responded in the normal way first – it sends the "traditional" 3 packet response – and then it sends an **additional** packet to act as the acknowledgement packet, and in this case with the top bit set to indicate success.

P.7 PC Communication Parameters

P.7.1 Baud Rate and Virtual Com Ports

The USB drivers on the PC side implement a virtual COM port.

P.7.2 Baud Rate and Data Format

The baud rate used is selectable and is either 38400 or 115200 baud.

The data format used is 8N1 (8 data bits, no parity, 1 stop bit).